Virtual Memory: Details

15-213/15-513: Introduction to Computer Systems 17th Lecture, June 14, 2024


Instructors:

Brian Railing

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Review: Virtual Addressing

- **Each process has its own virtual address space**
- Page tables map virtual to physical addresses
- Physical memory can be shared among processes




Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Review: Memory Accesses without VM

	s physical to cache
(sends to CPU


Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Review: Memory Accesses with VM




Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Review: Memory Accesses with VM




Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Review: Memory Accesses with VM




Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Review: The problem



Review: the problem (with k-level page tables)



Today

Page Faults


Conceptual Quiz

- Concrete examples of virtual memory systems
 - "Simple memory system" from CSAPP 9.6.4
 - Intel Core i7
- Nifty things virtual memory makes possible
 - Paging/swapping (disk as extra RAM)
 - Memory-mapped files (RAM as cache for disk)
 - Copy-on-write sharing

What happens on a page fault?

- What is a page fault?
- Why can they happen? How does the OS know?

OS tracks VM "areas"



Each area has permissions / purpose / etc

Types of Faults

1. This is a legal address

- Hard / Major faults "normal" page faults
- Soft / minor faults the OS took the page away, but has not reused it

2. The address is legal, but ...

The type of access is wrong, so "protection exception"

3. The address is not legal

Segmentation fault or bus error

Today

Page Faults

Conceptual Quiz

- Concrete examples of virtual memory systems
 - "Simple memory system" from CSAPP 9.6.4
 - Intel Core i7
- Nifty things virtual memory makes possible
 - Paging/swapping (disk as extra RAM)
 - Memory-mapped files (RAM as cache for disk)
 - Copy-on-write sharing

For a simple system with a one-level page table, what must the MMU do before fetching the PTE?

Before fetching the Page Table Entry (PTE) from a one-level page table in a simple system, the Memory Management Unit (MMU) performs the following sub-steps:

1.Virtual Address Splitting: The MMU splits the virtual address into two parts:

- 1. Virtual Page Number (VPN): The leftmost bits of the address represent the VPN.
- 2. Virtual Page Offset (VPO): The remaining bits indicate the offset within the page.

2.Indexing into Page Table: The VPN is used directly as an array index in the page table. The MMU looks up the corresponding PTE using the VPN.

Feel free to ask if you need further clarification!

For additional context and details, you can refer to the <u>lecture materials from Carnegie Mellon</u> <u>University¹²</u>

The MMU must know the *physical* address of the page table in order to read page table entries from memory. Why does it need a physical address?

The Memory Management Unit (MMU) requires the **physical address** of the page table for several reasons:

Address Translation: The MMO translates virtual addresses (used by the CPO) to physical addresses (used by RAM). To do this, it needs to access the page table.

Page Table Lookup: When a virtual address is accessed, the MMO uses the VPN (Virtual Page Number) to index into the page table. The resulting PTE (Page Table Entry) contains the physical address of the corresponding page frame in RAM.

Hardware Interaction: The MMU interacts directly with PAM and other hardware components. It needs the physical address to perform memory accesses efficiently.

Protection and Permissions: The page table entries also store information about page permissions (readonly, read-write, etc.) and protection flags. The MMU checks these flags to enforce memory protection. In summary, the physical address of the page table allows the MMU to perform address translation, look up PTEs, and manage memory efficiently. If you have further questions, feel free to ask!

Today

Page Faults

Conceptual Quiz


Concrete examples of virtual memory systems

- "Simple memory system" from CSAPP 9.6.4
- Intel Core i7
- Nifty things virtual memory makes possible
 - Paging/swapping (disk as extra RAM)
 - Memory-mapped files (RAM as cache for disk)
 - Copy-on-write sharing

Simple Memory System Example


Addressing

- 14-bit virtual addresses
- 12-bit physical address
- Page size = 64 bytes



Simple Memory System TLB

- 16 entries
- 4-way associative



VPN = 0b1101 = 0x0D


Translation Lookaside Buffer (TLB)

Set	Tag	PPN	Valid									
0	03	-	0	09	0D	1	00	-	0	07	02	1
1	03	2D	1	02	-	0	04	-	0	0A	-	0
2	02	-	0	08	-	0	06	-	0	03	-	0
3	07	-	0	03	0D	1	0A	34	1	02	-	0

Simple Memory System Page Table

Only showing the first 16 entries (out of 256)


	Valid	PPN	VPN]	Valid	PPN	VPN
	1	13	08		1	28	00
	1	17	09		0	_	01
	1	09	0 A]	1	33	02
	0	-	OB		1	02	03
	0	-	0C		0	-	04
$0x0D \rightarrow 0x2D$	1	2D	0D]	1	16	05
	1	11	OE		0	_	06
	1	0D	OF]	0	-	07



Simple Memory System Cache


- 16 lines, 4-byte cache line size
- Physically addressed
- Direct mapped

V[0b00001101101001] = V[0x369] P{0b101/101101001] = P[0xB69] = 0x15




Idx	Tag	Valid	B0	B1	B2	B3	Idx	Tag	Valid	B0	B1	B2	B3
0	19	1	99	11	23	11	8	24	1	3A	00	51	89
1	15	0	Ι	I	-	-	9	2D	0	-	-	-	-
2	1B	1	00	02	04	08	Α	2D	1	93	15	DA	3B
3	36	0	-	-	-	-	В	0B	0	-	-	-	-
4	32	1	43	6D	8F	09	С	12	0	-	-	-	-
5	0D	1	36	72	F0	1D	D	16	1	04	96	34	15
6	31	0	-	-	-	-	E	13	1	83	77	1B	D3
7	16	1	11	C2	DF	03	F	14	0	-	-	-	-


Address Translation Example



Intel Core i7 Memory System



End-to-end Core i7 Address Translation



P=0

Core i7 Level 1-3 Page Table Entries

63	62 52	51 12	11 9	8	7	6	5	4	3	2	1	0
XD	Unused	Page table physical base address	Unused	G	PS		Α	CD	wт	U/S	R/W	P=1

Available for OS	(page table location	on disk)
------------------	----------------------	----------

Each entry references a 4K child page table. Significant fields:

- P: Child page table present in physical memory (1) or not (0).
- R/W: Read-only or read-write access access permission for all reachable pages.
- U/S: user or supervisor (kernel) mode access permission for all reachable pages.
- WT: Write-through or write-back cache policy for the child page table.
- A: Reference bit (set by MMU on reads and writes, cleared by software).
- PS: Page size either 4 KB or 4 MB (defined for Level 1 PTEs only).
- Page table physical base address: 40 most significant bits of physical page table address (forces page tables to be 4KB aligned)
- XD: Disable or enable instruction fetches from all pages reachable from this PTE.

Core i7 Level 4 Page Table Entries


63	62 52	51 12	11 9	8	7	6	5	4	3	2	1	0
XD	Unused	Page physical base address	Unused	G		D	Α	CD	wт	U/S	R/W	P=1

Available for OS (page location on disk)	P=0)


Each entry references a 4K child page. Significant fields:

- P: Child page is present in memory (1) or not (0)
- R/W: Read-only or read-write access permission for child page
- U/S: User or supervisor mode access
- WT: Write-through or write-back cache policy for this page
- A: Reference bit (set by MMU on reads and writes, cleared by software)
- D: Dirty bit (set by MMU on writes, cleared by software)
- G: Global page (don't evict from TLB on task switch)
- Page physical base address: 40 most significant bits of physical page address (forces pages to be 4KB aligned)
- XD: Disable or enable instruction fetches from this page.

Core i7 Page Table Translation



Cute Trick for Speeding Up L1 Access



Observation

- Bits that determine CI identical in virtual and physical address
- Can index into cache while address translation taking place
- Generally we hit in TLB, so PPN bits (CT bits) available quickly
- "Virtually indexed, physically tagged"
- Cache carefully sized to make this possible

Today

- Page Faults
- Conceptual Quiz
- Concrete examples of virtual memory systems
 - "Simple memory system" from CSAPP 9.6.4
 - Intel Core i7

Nifty things virtual memory makes possible


- Memory-mapped files (RAM as cache for disk)
- Copy-on-write sharing

Memory-Mapped Files


- Paging = every page of a program's physical RAM is backed by some page of disk*
- Normally, those pages belong to swap space
- But what if some pages were backed by ... files?

* This is how it used to work 20 years ago. Nowadays, not always true.

Memory-Mapped Files



Memory-Mapped Files




Demo

Show mmap from sfs

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Copy-on-write sharing


- fork creates a new process by copying the entire address space of the parent process
 - That sounds slow
 - It is slow



Clever trick:

- Just duplicate the page tables
- Mark everything read only
- Copy only on write faults


Copy-on-write sharing



Clever trick:

- Just duplicate the page tables
- Mark everything read only
- Copy only on write faults

Copy-on-write sharing



Clever trick:

- Just duplicate the page tables
- Mark everything read only
- Copy only on write faults

Summary

- Multi-level page tables reduce total memory consumption of page tables
- Translation lookaside buffers reduce time cost of translation
- Real systems have 3 to 5 levels of page table
- Virtual memory makes nifty things possible
 - Memory protection and process isolation
 - Paging/swapping (disk as extra RAM)
 - Memory-mapped files (RAM as cache for disk)
 - Copy-on-write sharing

Why are one-level page tables impractical and how do multilevel page tables fix this problem?

A single-level page table covering the entire address space of a typical system would be much too large. For instance, with 4kB pages, a 48-bit address space, and a 8-byte PTE, a singlelevel page table would occupy 512 *gigabytes*, which is more RAM than most computers have.

Why is memory access slower with a multi-level page table than with a single-level page table?

A *k*-level page table requires *k* memory loads in order to determine the physical address. There is no spatial locality to these loads.

What is the Translation Lookaside Buffer (TLB), what problem does it solve, and when is it used?

The TLB is a small cache dedicated to storing mappings from virtual to physical addresses. It avoids the cost of lookups in a multi-level page table.

The MMU consults the TLB for each address as its first action; if there is a TLB hit, it does not need to fetch anything from the page table.

How does virtual memory interact with the memory cache(s)?

The cache's function is to speed up access to whatever data is most frequently used. The MMU sits "in between" the CPU and the cache; the cache works only with physical addresses. This means data from multiple processes may coexist in the cache (or compete for cache space).