

Bits, Bytes, and Integers – Part 2

15-213: Introduction to Computer Systems
3rd Lecture, May 25, 2017

Instructors:

Brian Railing

Autolab/TPZ/Gitlab accounts

- You should have all your accounts by now
 - You must be enrolled to get an account
 - If you are on waitlist, just keep on hanging in there
-
- Redshelf and digital content

First Assignment: Data Lab

- **Due: Thursday, June 1, 11:59:00 pm**
- **Last Possible Time to Turn in: Fri, June 2, 11:59PM**
- **Read the instructions carefully**
- **You should have started**
- **Seek help (office hours have started)**
- **Based on Lecture 2, 3 , and 4**
- **After today's lecture you know everything for the integer problems, float problems covered on Tuesday**

Summary From Last Lecture

- **Representing information as bits**
- **Bit-level manipulations**
- **Integers**
 - **Representation: unsigned and signed**
 - **Conversion, casting**
 - **Expanding, truncating**
 - **Addition, negation, multiplication, shifting**
- **Representations in memory, pointers, strings**
- **Summary**

Bit-Level Operations in C

■ Operations $\&$, $|$, \sim , \wedge Available in C

- Apply to any “integral” data type
 - long, int, short, char, unsigned
- View arguments as bit vectors
- Arguments applied bit-wise

■ Examples (Char data type)

- $\sim 0x41 \rightarrow 0xBE$
 - $\sim 0100\ 0001_2 \rightarrow 1011\ 1110_2$
- $\sim 0x00 \rightarrow 0xFF$
 - $\sim 0000\ 0000_2 \rightarrow 1111\ 1111_2$
- $0x69 \& 0x55 \rightarrow 0x41$
 - $0110\ 1001_2 \& 0101\ 0101_2 \rightarrow 0100\ 0001_2$
- $0x69 | 0x55 \rightarrow 0x7D$
 - $0110\ 1001_2 | 0101\ 0101_2 \rightarrow 0111\ 1101_2$

| Hex | Decimal | Binary |
|-----|---------|--------|
| 0 | 0 | 0000 |
| 1 | 1 | 0001 |
| 2 | 2 | 0010 |
| 3 | 3 | 0011 |
| 4 | 4 | 0100 |
| 5 | 5 | 0101 |
| 6 | 6 | 0110 |
| 7 | 7 | 0111 |
| 8 | 8 | 1000 |
| 9 | 9 | 1001 |
| A | 10 | 1010 |
| B | 11 | 1011 |
| C | 12 | 1100 |
| D | 13 | 1101 |
| E | 14 | 1110 |
| F | 15 | 1111 |

Logic Operations in C

■ Logic Operations: `&&`, `||`, `!`

- View 0 as “False”
- Anything nonzero as “True”
- Always return 0 or 1
- Early termination

■ Examples (char data type)

- `!0x41` → `0x00`
- `!0x00` → `0x01`
- `!!0x41` → `0x01`

- `0x69 && 0x55` → `0x01`
- `0x69 || 0x55` → `0x01`
- `p && *p` (avoids null pointer access)

Encoding Integers

Unsigned

$$B2U(X) = \sum_{i=0}^{w-1} x_i \cdot 2^i$$

Two's Complement

$$B2T(X) = -x_{w-1} \cdot 2^{w-1} + \sum_{i=0}^{w-2} x_i \cdot 2^i$$

Sign Bit



Two's Complement Examples (w = 5)

| | | | | | | | |
|------|---|-----|---|---|---|---|--|
| | | -16 | 8 | 4 | 2 | 1 | |
| 10 = | 0 | 1 | 0 | 1 | 0 | | |

$$8+2 = 10$$

| | | | | | | | |
|-------|---|-----|---|---|---|---|--|
| | | -16 | 8 | 4 | 2 | 1 | |
| -10 = | 1 | 0 | 1 | 1 | 0 | | |

$$-16+4+2 = -10$$

Unsigned & Signed Numeric Values

| X | $B2U(X)$ | $B2T(X)$ |
|------|----------|----------|
| 0000 | 0 | 0 |
| 0001 | 1 | 1 |
| 0010 | 2 | 2 |
| 0011 | 3 | 3 |
| 0100 | 4 | 4 |
| 0101 | 5 | 5 |
| 0110 | 6 | 6 |
| 0111 | 7 | 7 |
| 1000 | 8 | -8 |
| 1001 | 9 | -7 |
| 1010 | 10 | -6 |
| 1011 | 11 | -5 |
| 1100 | 12 | -4 |
| 1101 | 13 | -3 |
| 1110 | 14 | -2 |
| 1111 | 15 | -1 |

■ Equivalence

- Same encodings for nonnegative values

■ Uniqueness


- Every bit pattern represents unique integer value
- Each representable integer has unique bit encoding

■ Expression containing signed and unsigned int:


`int` is cast to `unsigned`!!

Sign Extension and Truncation

■ Sign Extension



■ Truncation



Today: Bits, Bytes, and Integers


- Representing information as bits
- Bit-level manipulations
- **Integers**
 - Representation: unsigned and signed
 - Conversion, casting
 - Expanding, truncating
 - **Addition, negation, multiplication, shifting**
- Representations in memory, pointers, strings
- Summary

Unsigned Addition

Operands: w bits



True Sum: $w+1$ bits



Discard Carry: w bits



■ Standard Addition Function

- Ignores carry output

■ Implements Modular Arithmetic

$$s = \text{UAdd}_w(u, v) = u + v \bmod 2^w$$


| | | | |
|---------------|-------------|------|-------|
| unsigned char | 1110 1001 | E9 | 223 |
| | + 1101 0101 | + D5 | + 213 |
| | 1 1011 1110 | 1BE | 446 |
| | 1011 1110 | BE | 190 |

| | Hex | Decimal | Binary |
|---|-----|---------|--------|
| 0 | 0 | 0000 | |
| 1 | 1 | 0001 | |
| 2 | 2 | 0010 | |
| 3 | 3 | 0011 | |
| 4 | 4 | 0100 | |
| 5 | 5 | 0101 | |
| 6 | 6 | 0110 | |
| 7 | 7 | 0111 | |
| 8 | 8 | 1000 | |
| 9 | 9 | 1001 | |
| A | 10 | 1010 | |
| B | 11 | 1011 | |
| C | 12 | 1100 | |
| D | 13 | 1101 | |
| E | 14 | 1110 | |
| F | 15 | 1111 | |

Visualizing (Mathematical) Integer Addition

■ Integer Addition

- 4-bit integers u, v
- Compute true sum $\text{Add}_4(u, v)$
- Values increase linearly with u and v
- Forms planar surface



Visualizing Unsigned Addition

■ Wraps Around


- If true sum $\geq 2^w$
- At most once

True Sum

2^{w+1}
 2^w
 0

Overflow

Modular Sum



Two's Complement Addition

Operands: w bits



True Sum: $w+1$ bits



Discard Carry: w bits



■ TAdd and UAdd have Identical Bit-Level Behavior

- Signed vs. unsigned addition in C:

```
int s, t, u, v;
```

```
s = (int) ((unsigned) u + (unsigned) v);
```

```
t = u + v
```


- Will give `s == t`

| | | | |
|---|-------------|------|-------|
| | 1110 1001 | E9 | -23 |
| + | 1101 0101 | + D5 | + -43 |
| | 1 1011 1110 | 1BE | 446 |
| | 1011 1110 | BE | -66 |

TAdd Overflow

■ Functionality

- True sum requires $w+1$ bits
- Drop off MSB
- Treat remaining bits as 2's comp. integer



Visualizing 2's Complement Addition


■ Values

- 4-bit two's comp.
- Range from -8 to +7

■ Wraps Around

- If $\text{sum} \geq 2^{w-1}$
 - Becomes negative
 - At most once
- If $\text{sum} < -2^{w-1}$
 - Becomes positive
 - At most once


NegOver



Characterizing TAdd

■ Functionality

- True sum requires $w+1$ bits
- Drop off MSB
- Treat remaining bits as 2's comp. integer



$$TAdd_w(u, v) = \begin{cases} u + v + 2^w & u + v < TMin_w \text{ (NegOver)} \\ u + v & TMin_w \leq u + v \leq TMax_w \\ u + v - 2^w & TMax_w < u + v \text{ (PosOver)} \end{cases}$$

Negation: Complement & Increment

- Negate through complement and increase

$$\sim x + 1 == -x$$

- Example

- Observation: $\sim x + x == 1111\dots111 == -1$

$$\begin{array}{r}
 x \quad \boxed{10011101} \\
 + \quad \sim x \quad \boxed{01100010} \\
 \hline
 -1 \quad \boxed{11111111}
 \end{array}$$

x = 15213

| | Decimal | Hex | Binary |
|-------------|---------------|--------------|--------------------------|
| x | 15213 | 3B 6D | 00111011 01101101 |
| ~x | -15214 | C4 92 | 11000100 10010010 |
| ~x+1 | -15213 | C4 93 | 11000100 10010011 |
| y | -15213 | C4 93 | 11000100 10010011 |

Complement & Increment Examples

$x = 0$

| | Decimal | Hex | Binary |
|--------------|---------|-------|-------------------|
| 0 | 0 | 00 00 | 00000000 00000000 |
| ~ 0 | -1 | FF FF | 11111111 11111111 |
| $\sim 0 + 1$ | 0 | 00 00 | 00000000 00000000 |

$x = \text{TMin}$


| | Decimal | Hex | Binary |
|--------------|---------|-------|-------------------|
| x | -32768 | 80 00 | 10000000 00000000 |
| $\sim x$ | 32767 | 7F FF | 01111111 11111111 |
| $\sim x + 1$ | -32768 | 80 00 | 10000000 00000000 |

Canonical counter example

Multiplication

- **Goal: Computing Product of w -bit numbers x, y**
 - Either signed or unsigned
- **But, exact results can be bigger than w bits**
 - Unsigned: up to $2w$ bits
 - Result range: $0 \leq x * y \leq (2^w - 1)^2 = 2^{2w} - 2^{w+1} + 1$
 - Two's complement min (negative): Up to $2w-1$ bits
 - Result range: $x * y \geq (-2^{w-1}) * (2^{w-1} - 1) = -2^{2w-2} + 2^{w-1}$
 - Two's complement max (positive): Up to $2w$ bits, but only for $(TMin_w)^2$
 - Result range: $x * y \leq (-2^{w-1})^2 = 2^{2w-2}$
- **So, maintaining exact results...**
 - would need to keep expanding word size with each product computed
 - is done in software, if needed
 - e.g., by “arbitrary precision” arithmetic packages

Unsigned Multiplication in C



■ Standard Multiplication Function

- Ignores high order w bits


■ Implements Modular Arithmetic

$$\text{UMult}_w(u, v) = u \cdot v \bmod 2^w$$

$$\begin{array}{r}
 1110 \ 1001 \\
 * \ 1101 \ 0101 \\
 \hline
 1100 \ 0001 \ 1101 \ 0010 \\
 \hline
 1101 \ 1101
 \end{array}$$

$$\begin{array}{r}
 \text{E9} \quad 223 \\
 * \ \text{D5} \quad 213 \\
 \hline
 \text{C1DD} \quad 47499 \\
 \hline
 \text{DD} \quad 221
 \end{array}$$

Signed Multiplication in C



■ Standard Multiplication Function

- Ignores high order w bits
- Some of which are different for signed vs. unsigned multiplication
- Lower bits are the same


| | | | |
|---|---------------------|------|-------|
| | 1110 1001 | E9 | -23 |
| * | 1101 0101 | * D5 | * -43 |
| | 1100 0001 1101 0010 | C1DD | 16896 |
| | 1101 1101 | DD | -35 |

Power-of-2 Multiply with Shift

■ Operation

- $u \ll k$ gives $u * 2^k$
- Both signed and unsigned


Operands: w bits



True Product: $w+k$ bits



Discard k bits: w bits




■ Examples

- $u \ll 3 \quad \quad \quad == \quad u * 8$
- $(u \ll 5) - (u \ll 3) == \quad u * 24$
- Most machines shift and add faster than multiply
 - Compiler generates this code automatically

Unsigned Power-of-2 Divide with Shift

■ Quotient of Unsigned by Power of 2

- $u \gg k$ gives $\lfloor u / 2^k \rfloor$
- Uses logical shift




| | Division | Computed | Hex | Binary |
|---------------------|-------------------|--------------|--------------|--------------------------|
| x | 15213 | 15213 | 3B 6D | 00111011 01101101 |
| x >> 1 | 7606.5 | 7606 | 1D B6 | 00011101 10110110 |
| x >> 4 | 950.8125 | 950 | 03 B6 | 00000011 10110110 |
| x >> 8 | 59.4257813 | 59 | 00 3B | 00000000 00111011 |

Signed Power-of-2 Divide with Shift

■ Quotient of Signed by Power of 2

- $x \gg k$ gives $\lfloor x / 2^k \rfloor$
- Uses arithmetic shift
- Rounds wrong direction when $u < 0$




| | Division | Computed | Hex | Binary |
|-----------|-------------|----------|-------|-------------------|
| y | -15213 | -15213 | C4 93 | 11000100 10010011 |
| $y \gg 1$ | -7606.5 | -7607 | E2 49 | 11100010 01001001 |
| $y \gg 4$ | -950.8125 | -951 | FC 49 | 11111100 01001001 |
| $y \gg 8$ | -59.4257813 | -60 | FF C4 | 11111111 11000100 |

Correct Power-of-2 Divide

■ Quotient of Negative Number by Power of 2

- Want $\lceil \mathbf{x} / 2^k \rceil$ (Round Toward 0)
- Compute as $\lfloor (\mathbf{x} + 2^k - 1) / 2^k \rfloor$
 - In C: $(\mathbf{x} + (1 \ll k) - 1) \gg k$
 - Biases dividend toward 0


Case 1: No rounding



Biassing has no effect

Correct Power-of-2 Divide (Cont.)

Case 2: Rounding



Biasing adds 1 to final result

Today: Bits, Bytes, and Integers

- Representing information as bits
- Bit-level manipulations
- **Integers**
 - Representation: unsigned and signed
 - Conversion, casting
 - Expanding, truncating
 - Addition, negation, multiplication, shifting
 - **Summary**
- Representations in memory, pointers, strings

Arithmetic: Basic Rules

■ Addition:

- Unsigned/signed: Normal addition followed by truncate, same operation on bit level
- Unsigned: addition mod 2^w
 - Mathematical addition + possible subtraction of 2^w
- Signed: modified addition mod 2^w (result in proper range)
 - Mathematical addition + possible addition or subtraction of 2^w

■ Multiplication:

- Unsigned/signed: Normal multiplication followed by truncate, same operation on bit level
- Unsigned: multiplication mod 2^w
- Signed: modified multiplication mod 2^w (result in proper range)

Why Should I Use Unsigned?

■ *Don't* use without understanding implications

- Easy to make mistakes

```
unsigned i;  
for (i = cnt-2; i >= 0; i--)  
    a[i] += a[i+1];
```

- Can be very subtle

```
#define DELTA sizeof(int)  
int i;  
for (i = CNT; i-DELTA >= 0; i-= DELTA)  
    . . .
```

Counting Down with Unsigned

■ Proper way to use unsigned as loop index

```
unsigned i;  
for (i = cnt-2; i < cnt; i--)  
    a[i] += a[i+1];
```

■ See Robert Seacord, *Secure Coding in C and C++*

- C Standard guarantees that unsigned addition will behave like modular arithmetic
 - $0 - 1 \rightarrow UMax$

■ Even better

```
size_t i;  
for (i = cnt-2; i < cnt; i--)  
    a[i] += a[i+1];
```

- Data type `size_t` defined as unsigned value with length = word size
- Code will work even if `cnt = UMax`
- What if `cnt` is signed and `< 0`?

Why Should I Use Unsigned? (cont.)

- **Do Use When Performing Modular Arithmetic**
 - Multiprecision arithmetic
- **Do Use When Using Bits to Represent Sets**
 - Logical right shift, no sign extension
- **Do Use In System Programming**
 - Bit masks, device commands,...

Integer Arithmetic Example

unsigned char

| | | |
|-------------|------|------|
| 1111 0011 | F3 | 243 |
| + 0101 0010 | + 52 | + 82 |
| 1 0100 0101 | 145 | 325 |
| 0101 0101 | 45 | 69 |

unsigned char


| | | |
|-------------|------|-----|
| 0001 1001 | 19 | 25 |
| * 0000 0010 | * 02 | * 2 |
| 0 0011 0010 | 032 | 50 |
| 0011 0010 | 32 | 50 |

| Hex | Decimal | Binary |
|-----|---------|--------|
| 0 | 0 | 0000 |
| 1 | 1 | 0001 |
| 2 | 2 | 0010 |
| 3 | 3 | 0011 |
| 4 | 4 | 0100 |
| 5 | 5 | 0101 |
| 6 | 6 | 0110 |
| 7 | 7 | 0111 |
| 8 | 8 | 1000 |
| 9 | 9 | 1001 |
| A | 10 | 1010 |
| B | 11 | 1011 |
| C | 12 | 1100 |
| D | 13 | 1101 |
| E | 14 | 1110 |
| F | 15 | 1111 |

Today: Bits, Bytes, and Integers

- Representing information as bits
- Bit-level manipulations
- Integers
 - Representation: unsigned and signed
 - Conversion, casting
 - Expanding, truncating
 - Addition, negation, multiplication, shifting
 - Summary
- **Representations in memory, pointers, strings**

Byte-Oriented Memory Organization



- **Programs refer to data by address**
 - Conceptually, envision it as a very large array of bytes
 - In reality, it's not, but can think of it that way
 - An address is like an index into that array
 - and, a pointer variable stores an address
- **Note: system provides private address spaces to each “process”**
 - Think of a process as a program being executed
 - So, a program can clobber its own data, but not that of others


Machine Words

- **Any given computer has a “Word Size”**
 - Nominal size of integer-valued data
 - and of addresses
 - Until recently, most machines used 32 bits (4 bytes) as word size
 - Limits addresses to 4GB (2^{32} bytes)
 - Increasingly, machines have 64-bit word size
 - Potentially, could have 18 EB (exabytes) of addressable memory
 - That's 18.4×10^{18}
 - Machines still support multiple data formats
 - Fractions or multiples of word size
 - Always integral number of bytes

Word-Oriented Memory Organization

■ Addresses Specify Byte Locations

- Address of first byte in word
- Addresses of successive words differ by 4 (32-bit) or 8 (64-bit)



Example Data Representations

| C Data Type | Typical 32-bit | Typical 64-bit | x86-64 |
|----------------------|----------------|----------------|--------|
| <code>char</code> | 1 | 1 | 1 |
| <code>short</code> | 2 | 2 | 2 |
| <code>int</code> | 4 | 4 | 4 |
| <code>long</code> | 4 | 8 | 8 |
| <code>float</code> | 4 | 4 | 4 |
| <code>double</code> | 8 | 8 | 8 |
| <code>pointer</code> | 4 | 8 | 8 |

Byte Ordering


- So, how are the bytes within a multi-byte word ordered in memory?
- Conventions
 - Big Endian: Sun, PPC Mac, *Internet*
 - Least significant byte has highest address
 - Little Endian: *x86*, ARM processors running Android, iOS, and Windows
 - Least significant byte has lowest address

Byte Ordering Example


■ Example

- Variable x has 4-byte value of 0x01234567
- Address given by &x is 0x100

Big Endian



Little Endian



Representing Integers


Decimal: 15213

Binary: 0011 1011 0110 1101


Hex: 3 B 6 D

`int A = 15213;`


Increasing addresses
↓



`long int C = 15213;`



`int B = -15213;`



Two's complement representation

Examining Data Representations

■ Code to Print Byte Representation of Data

- Casting pointer to unsigned char * allows treatment as a byte array

```
typedef unsigned char *pointer;

void show_bytes(pointer start, size_t len){
    size_t i;
    for (i = 0; i < len; i++)
        printf("%p\t0x%.2x\n", start+i, start[i]);
    printf("\n");
}
```

Printf directives:

%p: Print pointer

%x: Print Hexadecimal

show_bytes Execution Example


```
int a = 15213;
printf("int a = 15213;\n");
show_bytes((pointer) &a, sizeof(int));
```

Result (Linux x86-64):

```
int a = 15213;
0x7ffffb7f71dbc    6d
0x7ffffb7f71dbd    3b
0x7ffffb7f71dbe    00
0x7ffffb7f71dbf    00
```

Representing Pointers

```
int B = -15213;  
int *P = &B;
```



Different compilers & machines assign different locations to objects

Even get different results each time run program

Representing Strings


```
char S[6] = "18213";
```

■ Strings in C

- Represented by array of characters
- Each character encoded in ASCII format
 - Standard 7-bit encoding of character set
 - Character "0" has code 0x30
 - Digit i has code $0x30+i$
- String should be null-terminated
 - Final character = 0

■ Compatibility

- Byte ordering not an issue



Reading Byte-Reversed Listings

■ Disassembly

- Text representation of binary machine code
- Generated by program that reads the machine code

■ Example Fragment

| Address | Instruction Code | Assembly Rendition |
|----------|----------------------|------------------------|
| 8048365: | 5b | pop %ebx |
| 8048366: | 81 c3 ab 12 00 00 | add \$0x12ab, %ebx |
| 804836c: | 83 bb 28 00 00 00 00 | cmpl \$0x0, 0x28(%ebx) |

■ Deciphering Numbers

- Value: 0x12ab
- Pad to 32 bits: 0x000012ab
- Split into bytes: 00 00 12 ab
- Reverse: ab 12 00 00

Integer C Puzzles

Initialization

```
int x = foo();
int y = bar();
unsigned ux = x;
unsigned uy = y;
```

| | | | |
|---|---------------|-----------------------------------|---|
| <code>x < 0</code> | \Rightarrow | <code>((x*2) < 0)</code> | ✗ |
| <code>ux >= 0</code> | | | ✓ |
| <code>x & 7 == 7</code> | \Rightarrow | <code>(x<<30) < 0</code> | ✓ |
| <code>ux > -1</code> | | | ✗ |
| <code>x > y</code> | \Rightarrow | <code>-x < -y</code> | ✗ |
| <code>x * x >= 0</code> | | | ✗ |
| <code>x > 0 && y > 0</code> | \Rightarrow | <code>x + y > 0</code> | ✗ |
| <code>x >= 0</code> | \Rightarrow | <code>-x <= 0</code> | ✓ |
| <code>x <= 0</code> | \Rightarrow | <code>-x >= 0</code> | ✗ |
| <code>(x -x)>>31 == -1</code> | | | ✗ |
| <code>ux >> 3 == ux/8</code> | | | ✓ |
| <code>x >> 3 == x/8</code> | | | ✗ |
| <code>x & (x-1) != 0</code> | | | ✗ |

Summary

- **Representing information as bits**
- **Bit-level manipulations**
- **Integers**
 - **Representation: unsigned and signed**
 - **Conversion, casting**
 - **Expanding, truncating**
 - **Addition, negation, multiplication, shifting**
- **Representations in memory, pointers, strings**
- **Summary**